
Recording Video

1. Purpose of the experiment

Realize video recording.

2. Experimental path source code


Enter the dog's system, end the dog program, enter "ip (ip is the dog's ip): 8888" in the browser, enter the password "yahboom"



and log in. Enter the path of **cd ~/DOGZILLA_Lite_class/2.Base Control/07.Play the video** and run **dog_recode_videos.ipynb** .

3. Experimental Phenomenon

After running the code, the dog will open the camera and collect 5 seconds of camera images, and save them to the file /home/pi/xgoVideos/. The name is **myvidoes.mp4**



4. Main source code analysis

xgoVideoRecord(filename="myvidoes",seconds=5)

Parameter name	Format	Input range	illustrate
filename (optional) default is "recode"	String	/	The file name of the recorded video will automatically add the extension mp4, and the recorded file path is /home/pi/xgoVideos
seconds (optional) The default value is 5	number	/	Length of the recording file (seconds)